

Project & Play 1

Popular Hymns for Church

~ ORGAN ~

Project & Play 2

Popular Hymns for Schools

~ PIANO ~

IMPORTANT – READ BEFORE USING THE DVD*

Incompatibility with Adobe Reader under Windows 10, 11

Project & Play is a compilation of over 300 hymns for the words and music in PDF format.

It was originally designed to be used with the Adobe Reader application. In 2010 Adobe released version X (10.0) which changed the way some media files were played (such as .mp3 music files) under Windows 7, 8 & 10.


The updated software meant that the hymn verses of Project & Play could still be projected but the music files would not play. However, by using different PDF application such as Foxit Reader, Project & Play can still be used.

Using Project & Play with macOS is not affected.


Install the Foxit PDF Reader app (before using this DVD)



- 1 Go to: www.foxit.com/pdf-reader
- 2 Click the “Download” button.
- 3 The Foxit website should detect which type of computer you are using (Windows, Mac, Linux etc).
- 4 Click the “Free Download” button.
- 5 The software will download to your web browser’s download folder.
- 6 At the download folder select “Open”.



- 7 If a window appears that says, “Do you want to allow this app to make changes to your system”, select “Yes”.



- 8 At the Foxit install window, click “Next” and follow the instructions.
- 9 Wait for Foxit PDF Reader to install.
- 10 Restart your computer/device.

Setting up for the first time

Change the Preferences

- 11 Open the Foxit Reader app.
- 12 Go to ‘File...’ and ‘Preferences’ and change the following...
 - Select ‘Documents’ and uncheck ‘Alert user when documents request Full Screen’
 - Select ‘File Associations’ and click on ‘Make default PDF viewer’
 - Select ‘General’ and uncheck ‘Show Advertisement’ and ‘Show floating promotion page’
 - Select ‘Trust Manager’ and uncheck ‘Enable Safe Reading Mode’
 - Select ‘Updater’ and check ‘Do not download and install updates automatically’

Foxit Reader Q&As

- Q** Won't stay in Full Screen Mode
A Press F11 on your keyboard.
- Q** How do I advance from one screen to the next
A Press the left (<-->) and (=>) right arrows on the keyboard.
- Q** Text is too large on the screen
A Press F11 on your keyboard.

* The music on this DVD can only be played through a computer with a DVD drive. Project & Play is a DVD data disc and not the same as a DVD movie disc.